

Register your i.LON®100 and design your control/command screens online with

# ONLINE.VISION

free of charge !





DotVision

Did you already load the <http://www.dotvision.com/onlinestudio/> web page and have ONLINE.VISION up and running in your preferred web browser on your computer ?

If you encounter any technical problem to load the ONLINE.VISION java applet, please send an eMail to [support@dotvision.com](mailto:support@dotvision.com) with details about screenshots of the situation.

Let's register your iLON100 to use ONLINE.VISION... online and free-of-charge !

1. Click on this icon in the main toolbar. It displays the tools to configure the connection to your iLON100 and the control/command objects that you'll use to control/command your network variables.
2. Click on the icon to configure the connection to your iLON100 and enter the TCP/IP address of your iLON100
3. Click on the button. If your iLON100 is connected, you'll read its NEURON ID in this field.



Licence	
Authorization ID	12-34-56-78-90-AB
Authorized	No

Connection	
ilon100Gateway	
Host	192.168.0.102
Port	80
Refresh rate (s)	5
Priority(0=Max:255=Min)	255
Authorized	
Licence	
Authorization ID	<input type="text"/>
Authorized	No
<input type="button" value="Ok"/> <input type="button" value="Cancel"/>	
Java Applet Window	

4. Click on the registration button in the Online.Vision web page to open the DotVision registration form
5. Enter your information in the fields of the form and the NEURON ID in the Neuron ID field. Then click on the SEND button.



Neuron ID *:	<input type="text" value="12-34-56-78-90-AB"/>
--------------	--

The DotVision Technical Support team will send you a confirmation of your registration for your iLON100 by eMail soon (usually within 24 hours).



### **Once you get the registration confirmation from DotVision...**

1. Go back to <http://www.dotvision.com/onlinestudio/> to run ONLINE.VISION in your preferred Web Browser.
2. Open your Online.Vision project or design a new project to control the iLON100 you've registered.
3. Make sure the TCP/IP address of your i.LON100 is entered correctly in the according field.
4. Click on the button in front of "Authorized". Online.Vision checks in the DotVision database whether the NEURON ID of your iLON100 is registered. If it is registered correctly, your project will be unlocked to control and command all the SNVTs of your iLON100 for unlimited time.

### **Get technical support from DotVision**

At DotVision, we have the passion for high quality project delivered to the customer in record time and profitable manner. To achieve this goal, the DotVision Technical Support team shall:

- Assist you to design your first project for free. If your i.LON@100 and/or your GC100 Gateways are accessible from our office, we could even share your project and help you design it remotely. Explain the features you'd like to include in your project and we'll do it for you.
- Assist you in all your projects if you subscribe to the "CLUB DOTVISION" (part number DV\_CLUB). The subscription fee is 1290 USD or 990 Euros per year and per person. Subscribers are entitled for receiving How To Video files, for getting assistance on specific projects and for unlimited technical support by eMail.
- Assist you during 2-hours "How-to" Online Training session using SKYPE and/or VNC tools. The price for this service is 220 Euros or 290 USD (part number : DV\_OTs).
- Design a project for you if you feel you don't have the time todo it your self. Usually, DotVision's package to design a Web Graphical project with ONLINE.VISION is priced 4 200 USD or 3 500 Euros or per project (to be confirmed depending on the Functional/Technical Specification of your project, i.e. description of your needs).

To **GET TECHNICAL SUPPORT**, contact the technical support team :

- By eMail : [support@dotvision.com](mailto:support@dotvision.com)
- By Phone : +33 1 47 70 25 25

To **BECOME A RESELLING PARTNER**, an **INTEGRATOR** or to **INTEGRATE ONLINE.VISION AS AN OEM COMPONENT** in your products, contact the DotVision Sales Team :

- By eMail : [contact@dotvision.com](mailto:contact@dotvision.com)
- By Phone : +33 1 47 70 25 25



## **SOFTWARE USAGE LICENSE Terms and Conditions**

This agreement is between DOTVISION and the users of the DOTVISION's software, i.e. "ONLINE.VISION i.LON100 Edition" (reference DV33-1010), hereafter called the "SOFTWARE PRODUCT". If you do not intend to honor this agreement, please exit now from the Web Page from which you're using the Software and do not use this online software.

Please read carefully this License Agreement before using this SOFTWARE PRODUCT. By using this SOFTWARE PRODUCT you agree to all of the terms of this Agreement. If you do not agree to all of the terms, do not use this SOFTWARE PRODUCT, and destroy all DotVision material.

The terms of this License Agreement supersede any other license agreements accompanying this SOFTWARE PRODUCT. If you accept the terms of this License Agreement by using SOFTWARE PRODUCT, then DotVision grants you a limited license to use this SOFTWARE PRODUCT for personal use or in your business or profession with the following limitations:

- + You are not allowed to use the SOFTWARE PRODUCT to control, monitor, send command and/or configure for more than 15 minutes in a row an i.LON@100 which Neuron ID (or identifier) is not registered in the usage license database from DotVision.
- + If you want the Neuron ID of your i.LON@100 to be registered in the central usage license database from DotVision, you must send the DotVision registration form in which you enter the Neuron ID of your iLON100 following the process described by DotVision in document OLV33\_7.

Once your iLON100 is registered in the DotVision usage license database, you are granted a non-exclusive right to use the SOFTWARE PRODUCT with the above-mentioned limitations. Use of the software means that you have loaded the program in a supported Web Browser and run it or have installed the program onto a computer, which is supported by the SOFTWARE PRODUCT, as mentioned in its User Guide.

Ownership and Title of the SOFTWARE PRODUCT remains with DotVision. You are not allowed to make copies, reproductions, translations or modifications of or to the SOFTWARE PRODUCT.

This SOFTWARE PRODUCT and other DotVision Software, Products, Logo or Graphics Files are copyright protected. No program, code, part, image, video clip, audio sample, text or computer generated sequence of images may be copied or used in any way by the user except as intended within the bounds of the single SOFTWARE PRODUCT.

Copies of the SOFTWARE PRODUCT and/or its documentation may not be distributed to anyone under any terms and conditions without written authorization from DotVision. You are not allowed to disassemble, create derivative works, modify, reverse engineer, adapt, decompile or translate the SOFTWARE PRODUCT.

You are not allowed to adapt, create derivative works, or translate any part of the documentation without the prior written consent of DotVision. You are not allowed to lease, rent, transfer, assign or sell the SOFTWARE PRODUCT to any other person. You may not transfer it electronically or using any other means from one computer to another. You are not allowed to develop or ask any other company to develop features, actions and software architectures that would be similar to or would have the same objectives as those contained within the SOFTWARE PRODUCT.

**\* NO WARRANTIES \***

**THE SOFTWARE AND ANY RELATED DOCUMENTATION IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR INFRINGEMENT. THE ENTIRE RISK ARISING OUT OF USE OR PERFORMANCE OF THE SOFTWARE REMAINS WITH YOU.**

**\* NO LIABILITY FOR DAMAGES \***

**IN NO EVENT SHALL DOTVISION OR ITS SUPPLIERS BE LIABLE FOR ANY DAMAGES WHATSOEVER, INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFIT, BUSINESS INTERRUPTION, LOSS OF BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF DOTVISION HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. BECAUSE OF SOME STATES / JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF LIABILITY FOR CONSEQUENTIAL OR INCIDENTAL DAMAGES, THE ABOVE LIMITATION MAY NOT APPLY TO YOU.**



**Copyright Notice** : DotVision's Software and this User Guide are Copyright © 2000-2006. All rights reserved. DotVision and DotVision's logo are trademarks of DotVision Inc.

No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or storing in a retrieval system, or translated into any language in any form without the prior written consent of DotVision.

**Trademark Notice** : DotVision®, DotVision Inc.®, DotVision Research®, DotVision Viewer®, DotVision Server®, DotVision Studio®, DotVision Navigation Suite®, eSpace®, IzoStudio® and DotSpace® trademarks and logos are registered trademarks of DotVision® in Europe and the United States of America. DotVision® is a trademark of DotVision Inc.®

## CONTACT AND SUPPORT INFORMATION

DOTVISION  
19 rue VIVIENNE  
75002 Paris  
FRANCE  
Tel: +33 1 47 70 25 25  
<http://www.dotvision.com>

Send any question about this document to [contact@dotvision.com](mailto:contact@dotvision.com).